

N76E003 BSP Guide

Directory Introduction for Nuvoton 8051 Family

Directory Information

Please extract the “N76E003_BSP_Keil_C51_V1.0.6.zip” file firstly, and confirm the following folder all contain.

This BSP folder contents:

Document	Driver reference manual and reversion history.
Common	The common usual subroutine include Timer delay and basic UART baud rate setting
Include	All include header file and define
Sample_Code	Driver sample code.
Startup	Startup file for N76E003

The information described in this document is the exclusive intellectual property of Nuvoton Technology Corporation and shall not be reproduced without permission from Nuvoton.

*Nuvoton is providing this document only for reference purposes of NuMicro microcontroller based system design.
Nuvoton assumes no responsibility for errors or omissions.*

All data and specifications are subject to change without notice.

For additional information or questions, please contact: Nuvoton Technology Corporation.

www.nuvoton.com

1 .\Document\

Nuvoton_N76E003_BSP_
Revision_History.pdf

This document shows the revision history of N76E003 BSP.

2 \Common

Common.c	UART0 Baud rate setting base on Time 1 or Timer 3, UART1 baud rate setting base on Timer 3
Delay.c	Timer0_Delay100us, Timer0_Delay1ms, Timer1_Delay10ms, Timer2_Delay500us, Timer3_Delay100ms setting

3 \Include

Common.h	Header file to extern function for Common.c
Delay.h	Header file of extern function for Delay.c
Function_Define.h	Function setting include GPIO initial, External pin interrupt trig mode, Timer value common value define, Timer 2 capture enable, PWM initial, ADC initial
N76E003.h	N76E003 SFR define header file
SFR_Macro.h	Extend N76E003 define for no-bit-addressable SFR with bit enable or disable function.

4 \Sample_Code

ADC_Bandgap	ADC band-gap input demo code
ADC_Bandgap_VDD_noDelay	ADC converts demo code with band-gap value to calculate the VDD value. Add 5 times average value test and judge bandgap mark to find the best value for calculate.
ADC_IO_Trig	ADC trig start polling or interrupt by special I/O
ADC_multi_channel	ADC different channel input alternate demo code.
ADC_Optimizing_16x	ADC convert 16 times average value to get an optimized value of the ADC convert result
ADC_PWM_Trig	ADC trig start by PWM cycle finish
ADC_Simple	ADC trig start polling or interrupt by SFR start bit
Clock_Out	N76E003 HIRC clock out setting
Fsys_Select	System clock select demo
GPIO	All GPIO quasi / push pull/ input only/ open drain four status initial setting and toggle out
I2C_EEPROM	I ² C module connect with external EEPROM read writer demo
I2C_Master-Slave	Two piece of N76E003 I ² C module connect, the master and slave demo code
IAP_AP-program-AP_Dataflash	IAP run in APROM to program APROM demo code, It's also used as program data flash area.
IAP_Dataflash_EEPROM	Customer use this macro, each time call this subroutine, can use Data flash as EEPROM mode, the process include read old data / erase / modify new code/ write in.
IAP_LD-Program-AP	IAP run in LDROM to program APROM. This function is use in ISP function.
IAP_ModifyHIRC	The function to modify HIRC value to 16.6MHz for UART baud rate over 38400 application system.
IAP_program_Config	Use code IAP function to modify CONFIG area.

IAP_Read_Bandgap	Use IAP command to read actually band-gap value for each N76E003.
IAP_Read_UID	Use IAP command to read the UID of each N76E003.
IAP_Read_UCID	Use IAP command to read the UCID of each N76E003.
Pin_Interrupt	Each GPIO of N76E003 can use as external interrupt pin. Trig IC wakeup from idle / power down mode.
PWM_DeadTime	PWM output with dead time insert initial setting
PWM_INT	PWM output with interrupt subroutine
PWM_Simple	Simple PWM output setting initial
SPI_Flash	Read / writer W25Q16 sample code.
SPI_Master-Slave	SPI connect with two N76E003, Include master and slave sample code, use interrupt and polling.
Timer01_mode_0	Timer 0 and Timer 1 mode 0 demo code
Timer01_mode_1	Timer 0 and Timer 1 mode 1 demo code
Timer01_mode_2	Timer 0 and Timer 1 mode 2 demo code
Timer01_mode_3	Timer 0 and Timer 1 mode 3 demo code
Timer2_AutoReload_Capture	Timer 2 capture with compare function demo code
Timer2_AutoReload_Delay	Timer 2 auto reload mode for delay function demo code
Timer3	Timer 3 delay counter demo code
UART0	UART0 demo code
UART0_mode_3	UART0 mode 3 with TB8/RB8 function
UART0_printf	Setting send from UART0 TX pin when call printf function sample project.
UART1	UART1 demo code
UART1_printf	Setting send from UART1 TX pin when call printf function sample project.

WakeupTimer_INT	Wakeup timer with interrupt subroutine demo code
Watchdog_INT	Watch dog without reset, only interrupt function initial
Watchdog_Reset	Watch dog reset MCU function setting initial
Watchdog_Reset_Disable	Use IAP command to modify CONFIG WDT reset setting, disable WDT reset function. Once WDT reset is setting enable by CONFIG, only this way can disable it.
xRAM_768B	XRAM 768 bit test, assembler and c code compiler in one project demo

5 REVISION HISTORY

Date	Revision	Description
2016.12.28	1.00	Initially issued.
2017.2.1	1.01	1. Added HIRC modify 2. Added SPI master / slave control demo code include interrupt and polling
2017.6.20	1.02	1. Added POR disable instruction in startup.a51 2. Added ADC read band-gap and calculate VDD value demo 3. Added ADC 16 times optimize demo 4. Added read UCID sample code
2017.9.26	1.03	1. Modified ADC read band-gap and calculate VDD value demo
2017.12.28	1.04	1. Added Watchdog_Reset_Disable demo.
2018.1.29	1.05	1. Added printf_UART1 demo project 2. Removed ADD_Bandgap_VDD project, added ADD_Bandgap_VDD_noDelay project
2018.7.2	1.06	1. Modified printf_UART1 to UART1_printf 2. Added "UART0_printf" project 3. Added "ADC_multi_channel" project

Important Notice

Nuvoton Products are neither intended nor warranted for usage in systems or equipment, any malfunction or failure of which may cause loss of human life, bodily injury or severe property damage. Such applications are deemed, "Insecure Usage".

Insecure usage includes, but is not limited to: equipment for surgical implementation, atomic energy control instruments, airplane or spaceship instruments, the control or operation of dynamic, brake or safety systems designed for vehicular use, traffic signal instruments, all types of safety devices, and other applications intended to support or sustain life.

All Insecure Usage shall be made at customer's risk, and in the event that third parties lay claims to Nuvoton as a result of customer's Insecure Usage, customer shall indemnify the damages and liabilities thus incurred by Nuvoton.

*Please note that all data and specifications are subject to change without notice.
All the trademarks of products and companies mentioned in this datasheet belong to their respective owners.*